

Title

AR Epilepsy Education App:

Learning about the brain with interactive characters.

Subtitle

Documentation for developers and users

Table of Contents

1. Introduction	3
1.1. Overview	3
1.2. Purpose and target audience	3
1.3. System Requirements.....	3
2. Application Functionality	3
2.1. Image Targets and Recognition	3
2.1.1. List of image targets	3
2.1.2. Triggering mechanism (how are objects rendered/scripts run).....	7
2.1.3. Troubleshooting for target recognition issues.....	11
2.2. Characters and Interactions	12
2.2.1. Introduction of the characters	12
2.2.2. Dialogue structure and content.	12
2.3. Educational Content	14
2.3.1. Topics covered about the brain.....	14
2.3.2. Source of information	15
3. Technical Specifications.....	15
3.1. Development platform and tools.....	15
3.2. Scripts and Logic	15
3.3. Importing Vuforia	24

1. Introduction

1.1. Overview

An easy-to-use application for learning basic information about the brain parts and their functionality. By using 3D – animation, this app provides visual presentation of the brain.

1.2. Purpose and target audience

The purpose of this application is to provide basic information about the brain to the children.

1.3. System Requirements

Should have at least Android 7.0 and 5 MP camera.

2. Application Functionality

2.1. Image Targets and Recognition

2.1.1. List of image targets

- barcode0022_scaled_scaled



- barcode0033_scaled_scaled



- barcode0044_scaled_scaled



- barcode0055_scaled_scaled



- Image006_scaled



- Image007_scaled



- Image008_scaled



- Image009_scaled



- Image010_scaled



- Image011_scaled



- Image012_scaled



- Image013_scaled



- Image014_scaled



- Image015_scaled



- Image016_scaled



- Image017_scaled



- Image018_scaled




2.1.2. Triggering mechanism (how are objects rendered/scripts run)


Physical images printed with unique patterns are recognized by the camera and act as virtual buttons. When the camera detects and tracks the image, the associated 3D object or animation is triggered. When the 3D object or animation is triggered, it executes the already selected method from a particular script.

Steps:


1. Select image target from the **hierarchy** window.




2. On the **Inspector** window, there is the functionality to be set when the image target is found.




3. Select **Dialogue** object from **hierarchy** window to the **On Target Found()** in Inspector window and drop it in under the object area below “Runtime Only” option menu





4. Next, click on this menu button and choose your required script, then select the method/function in that script which you want to run.



The same goes for the **On Target Lost ()** function.

2.1.3. Troubleshooting for target recognition issues

When your phone fails to detect the image target, then make sure that your camera lens is clean, if that doesn't fix the problem then restart the app. This will probably fix the problem. If the issue persists or the incorrect target is detected, then change the image target.

2.2. Characters and Interactions


2.2.1. Introduction of the characters


There are two characters, a girl named **Tina** and a doctor named **Rio**. Tina asks questions about human brain and Rio answers them in an understandable way.

Both characters have walking, running and other animations which are executed randomly. But they remain at the same place.


2.2.2. Dialogue structure and content.


The dialogues are included as a **3D-Object** in which the text component is included.





The orientation of the captions is controlled by the position and scale of this object





2.3. Educational Content

2.3.1. Topics covered about the brain.

The basic knowledge about human brain is taught. The names of the basic parts of the brain were mentioned and their functionality is also discussed.

2.3.2. Source of information

The information has been collected mainly from the **National Institute of Neurological Disorders and Stroke**.

<https://www.ninds.nih.gov/health-information/public-education/brain-basics/brain-basics-know-your-brain>

3. Technical Specifications

3.1. Development platform and tools

This application has been developed in **Unity** engine with the help of **Vuforia engine**. All the characters and brain model are made with unity while the AR features and image target detection features are implemented using Vuforia engine.

3.2. Scripts and Logic

The basic requirement was to make the characters talk, display subtitles and highlight different parts of the brain.

At first, an object named **Dialogues** is made as child object of image target, then a script named **dialogueManager.cs** is attached to it, the **dialogueManager.cs** has two arrays, One array named as **scenedialogue** stores dialogues while other array named as **audios** stores audios of the characters.

The dialogues in **scenedialogue** and **audios** arrays is put as an object.

The script works in such a way that the second dialogue of the characters is played after some delay, this delay is implemented using **yield** function which pauses all the processes for a certain period of specified time.

```

C# dialogueManager.cs X
1  using System.Collections;
2      using System.Collections.Generic;
3  using UnityEngine;
4
5  1 asset usage
6  public class dialogueManager : MonoBehaviour
7  {
8      public GameObject[] scenedialogue; 1 asset usage
9      public GameObject[] audios; 1 asset usage
10     // Start is called before the first frame update
11     public void Dialoman()
12     {
13         StartCoroutine(routine: waiter());
14     }
15
16     // Update is called once per frame
17
18     Frequently called 2 usages
19     IEnumerator waiter()
20     {
21         yield return new WaitForSeconds(3);
22
23         scenedialogue[0].SetActive(true);
24         audios[0].SetActive(true);
25         audios[0].GetComponent<AudioSource>().Play();
26
27         //Wait for 4 seconds
28         yield return new WaitForSeconds(7);
29         scenedialogue[0].SetActive(false);
30         scenedialogue[1].SetActive(true);
31         audios[0].SetActive(false);
32         audios[1].SetActive(true);
33         audios[1].GetComponent<AudioSource>().Play();
34
35         //Wait for 2 seconds
36         yield return new WaitForSeconds(3);
37
38         scenedialogue[1].SetActive(false);
39         scenedialogue[2].SetActive(true);
40         audios[1].SetActive(false);
41         audios[2].SetActive(true);

```





```

40      audios[2].GetComponent<AudioSource>().Play();
41      /*
42      yield return new WaitForSeconds(3);
43
44      scenedialogue[2].SetActive(false);
45      scenedialogue[3].SetActive(true);
46      audios[2].SetActive(false);
47      audios[3].SetActive(true);
48      audios[3].GetComponent<AudioSource>().Play();
49
50      yield return new WaitForSeconds(3);
51
52      scenedialogue[3].SetActive(false);
53      scenedialogue[4].SetActive(true);
54      audios[3].SetActive(false);
55      audios[4].SetActive(true);
56      audios[4].GetComponent<AudioSource>().Play();
57
58      yield return new WaitForSeconds(3);
59
60      scenedialogue[4].SetActive(false);
61      scenedialogue[5].SetActive(true);
62      audios[4].SetActive(false);
63      audios[5].SetActive(true);
64      audios[5].GetComponent<AudioSource>().Play();
65
66      yield return new WaitForSeconds(3);
67
68      scenedialogue[5].SetActive(false);
69      scenedialogue[6].SetActive(true);
70      audios[5].SetActive(false);
71      audios[6].SetActive(true);
72      audios[6].GetComponent<AudioSource>().Play();*/
73  }
74
75  1 asset usage
76  public void Stopco()
77  {
78      StopCoroutine(routine: waiter());
79  }

```

The commented code is written there in case they are needed, but it is a better approach to use loops for it.

After that the **text(legacy)** object is placed in which the subtitles are written



Now, lets see the part where brain comes in,

In this case, there are some times when we needed different parts of the brain to be separated in order to show them clearly.

This was done by using script named **Two_People_Dialogues.cs** .

This script is similar to **dialogueManager.cs** but it has additional controls for brain model's appearance.

The only useable script used with **Two_People_Dialogues.cs** is **ZoomIn.cs** script.


This **zoomIn.cs** script helps in increasing the size of the brain to show it more clearly. It also takes the brain part's number (for example in this case the brain has 5 parts, and if want to take out part 2) then we drag the brain part and put it in the array named as **brainPartToTakeOut**.




Important

It is very important to write the brain model's name in the input string named **brainName** who's parts are to be separated.

If I have brain model's name **brain23_9**



then I must write it correctly in here:



```

C# zoomIn.cs X
1  using System.Collections;
2      using System.Collections.Generic;
3      using UnityEngine;
4      using UnityEngine;
5      using UnityEngine.Serialization;
6      using UnityEngine.UIElements;
7
8      5 asset usages 1 usage 1 exposing API
9      public class zoomIn : MonoBehaviour
10     {
11         public string brainName; 5 Changed in 1 asset
12         public GameObject[] characters; 5 Serializable
13         public GameObject[] brainPartToTakeOut; 5 Serializable
14         public Vector3 partNewPosition; 5 Serializable
15         public float zoomDuration = 3f; // Adjust the duration of the zoom
16         public Vector3 targetScale; 5 Serializable
17         public Vector3 changePos; 5 Serializable
18         public bool isContinued = false; 5 "true"
19         public Vector3 target; 5 Serializable
20
21         Frequently called 2 usages
22         public void brainZoomIn()
23         {
24             if (isContinued == false)
25             {
26                 StartCoroutine(routine: SmoothZoomIn());
27             }
28             else
29             {
30                 simpleZoomIn();
31             }
32         }
33     }
34
35
36
37
38
39
40

```

```

41     }
42
43     void simpleZoomIn(){...}
44
45     IEnumerator SmoothZoomIn()
46     {
47         for (int i = 0; i < brainPartToTakeOut.Length; i++)
48         {
49             brainPartToTakeOut[i].transform.localPosition = Vector3.Lerp(a: brainPartToTakeOut[i].transform.position, b: partNewPosition, t: 1);
50         }
51
52         Transform brainTransform = GameObject.Find(brainName).transform;
53
54         Vector3 startScale = brainTransform.localScale;
55
56         Vector3 startPosition = brainTransform.localPosition;
57
58         float elapsedTime = 0f;
59
60         for (int i = 0; i < characters.Length; i++)
61         {
62             characters[i].SetActive(false);
63         }
64
65         while (elapsedTime < zoomDuration)
66         {
67             brainTransform.localScale = Vector3.Lerp(a: startScale, b: targetScale, t: elapsedTime / zoomDuration);
68             brainTransform.localPosition = Vector3.Lerp(a: startPosition, b: changePos, t: elapsedTime/zoomDuration);
69             elapsedTime += Time.deltaTime;
70             yield return null;
71         }
72
73         // Ensure that the scale is set to the exact target scale when the coroutine finishes
74         brainTransform.localScale = targetScale;
75     }
76 }

```

At the last, there is another script named as **allPartsOfBrain.cs** this script is specially made to separate all parts of the brain.

```

1  using System;
2      using System.Collections;
3      using System.Collections.Generic;
4      using UnityEngine;
5
6      2 asset usages 1 usage 1 exposing API
7      ^o public class allPartsOfBrain : MonoBehaviour
8      {
9          private float zoomDuration = 5f;
10         public GameObject part1;  Changed in 1 asset
11         public Vector3 PosPart1;  Serializable
12         public GameObject part2;  Changed in 1 asset
13         public Vector3 PosPart2;  Serializable
14         public GameObject part3;  Changed in 1 asset
15         public Vector3 PosPart3;  Serializable
16         public GameObject part4;  Changed in 1 asset
17         public Vector3 PosPart4;  Serializable
18         public GameObject part5;  Changed in 1 asset
19         public Vector3 PosPart5;  Serializable
20
21
22         Frequently called 1 usage
23         public void PrZoom()
24         {
25             StartCoroutine(routine: Expands());
26         }
27
28         Frequently called 1 usage
29         IEnumerator Expands()
30         {
31             float elapsedTime = 0f;
32             while (elapsedTime < zoomDuration)
33             {
34                 part1.transform.localPosition = Vector3.Lerp(a: part1.transform.position, b: PosPart1, t: elapsedTime/zoomDuration);
35                 part2.transform.localPosition = Vector3.Lerp(a: part2.transform.position, b: PosPart2, t: elapsedTime/zoomDuration);
36                 part3.transform.localPosition = Vector3.Lerp(a: part3.transform.position, b: PosPart3, t: elapsedTime/zoomDuration);
37                 part4.transform.localPosition = Vector3.Lerp(a: part4.transform.position, b: PosPart4, t: elapsedTime/zoomDuration);
38                 part5.transform.localPosition = Vector3.Lerp(a: part5.transform.position, b: PosPart5, t: elapsedTime/zoomDuration);
39                 elapsedTime += Time.deltaTime;
40                 yield return null;
41             }
42         }

```

Now, lastly for zooming in and out of the brain model, the **touchZoom.cs** script has been used. Just apply this script to the brain's model and it will work fine.

```

C# touchZoom.cs ×
1  using System.Collections;
2  using System.Collections.Generic;
3  using UnityEngine;
4
5  public class touchZoom : MonoBehaviour
6  {
7      // Start is called before the first frame update
8      private float initialDistance;
9      private Vector3 initialScale;
10
11     void Start()
12     {
13
14     }
15
16     void Update(){
17         // scale using pinch involves two touches
18         // we need to count both the touches, store it somewhere, measure the distance between pinch
19         // and scale gameobject depending on the pinch distance
20         // we also need to ignore if the pinch distance is small (cases where two touches are registered accidentally)
21
22
23         if(Input.touchCount == 2)
24         {
25             var touchZero = Input.GetTouch(0);
26             var touchOne = Input.GetTouch(1);
27
28             // if any one of touchzero or touchOne is cancelled or maybe ended then do nothing
29             if(touchZero.phase == TouchPhase.Ended || touchZero.phase == TouchPhase.Canceled ||
30                touchOne.phase == TouchPhase.Ended || touchOne.phase == TouchPhase.Canceled)
31             {
32                 return; // basically do nothing
33             }
34
35             if(touchZero.phase == TouchPhase.Began || touchOne.phase == TouchPhase.Began)
36             {
37                 initialDistance = Vector2.Distance(touchZero.position, touchOne.position);
38                 initialScale = gameObject.transform.localScale;
39             }
40
41         }
42         else // if touch is moved
43         {
44             var currentDistance = Vector2.Distance(touchZero.position, touchOne.position);
45
46             //if accidentally touched or pinch movement is very very small
47             if (Mathf.Approximately(initialDistance, 0))
48             {
49                 return; // do nothing if it can be ignored where initial distance is very close to zero
50             }
51
52             var factor = currentDistance / initialDistance;
53             gameObject.transform.localScale = initialScale * factor; // scale multiplied by the factor we calculated
54         }
55     }
56 }
57


```

3.3. Importing Vuforia

The Vuforia engine is used to make image targets and help display objects on them.

To get Vuforia engine, first we have to go to their website
<https://developer.vuforia.com/>

Then we signup, after that we go to **target manager**



The screenshot shows the Vuforia developer portal interface. The top navigation bar includes links for Home, Downloads, Library, Support, and Pricing. Below this, a secondary navigation bar contains links for Account, Licenses, Credentials, and Target Manager, with 'Target Manager' highlighted by a red circle. The main content area is titled 'Target Manager' and includes a green 'Add Database' button. Below the title, there is a search bar and a table listing existing databases.

Database	Type	Targets	Date Modified
ar_images	Device	1	Jan 08, 2024
ep-AR_database	Device	18	Jan 16, 2024
for_animation	Device	1	Jan 09, 2024

From there, we click on **Add Database**.

We give it a **Name** and choose **Device** then click on **Create**.

Create Database

Database Name *

mydb

Type:

- ☒ Device
- ☐ Cloud
- ☐ VuMark

Cancel

Create

Then we click on **Add Target** button. Then we upload an image which could be a good target (don't use too much decorated image or too dull image, this won't be a better image target).

Then after adding desired amount of images, click on **download database** button

Targets (0)

Add Target

Download Database (All)

<input type="checkbox"/> Target Name	Type	Rating ⓘ	Status ▼	Date Modified
--------------------------------------	------	----------	----------	---------------

After that go to **Licenses** tab

Licenses

[Get Basic](#)
[Buy Premium](#)
[Buy Cloud Add On](#)

[Learn more](#) about licensing.
Create a license key for your application.

Name	Primary UUID ^①	Type	Status [▼]	Date Modified
ep_ar_p	N/A	Basic	Active	Jan 15, 2024
for_animations	N/A	Basic	Active	Jan 09, 2024
AR_IMG	N/A	Basic	Active	Jan 08, 2024

Click on **Get Basic** and give your license a name, after creating, you'll get something like that

[License Key](#)
[Usage](#)

Please copy the license key below into your app

```
Aazm7uD/////AAABmf4pZ5CuBEWGrYPLHn+o/zY0vGBKXDdHJjzh1Z+K+aJ63pwHE3z8MyXuuDfrI5Y0Yewcq
u/A/CmdBjhb06iH0N5KBYzyvEIQ2Y6gj1Irv/gOR0LkIf2uVRHWNLBWWw22CJsV0oMCj5f69tn0hmave7733n
EpkZAY7yadM70iynSF967bNDckdYEMD87fWYzjCo1ROx1/+U9EP1I8uigxqI9MePqCq2c1BSp0V4nXVaFT56wA
pYRiRb38JEGm5rVJ4tjIwMhYM9uaOvrZ43TXkeeIv4F/41bnJjsIxFcXEXSpwvhEoo4oOiQbOvx+U066gNP3m+
EF6ngYDD5HXEG4bC658MpI6oXHNZuZp5cKZXq
```

Plan Type: Basic


Status: Active

Created: Jan 15, 2024 19:23


License UUID: 2c06f833a9ee4c96ad1d541198ef66e8

History:


Copy the license key and paste it in the **AR Camera** in unity engine.




Click here




Then drop down **Global** and paste your **License key** there



Then to create image targets, simply **Right-Click** in hierarchy section and do the following



In image target's properties on right side of screen, you can select your imported Vuforia database and select your image targets from there



The End